



Liv - Girl's Top

No. 1004-194-9745

Materials

3 (3, 3, 4) skeins of 1.8 oz. (50 g)
Rainbow 8/4, color 27

Crochet hook US size E/4 (3,5 mm)
4 buttons

Yarn quality

Rainbow 8/4, Hobbii
100% cotton, 50 g = 170 m

Crochet gauge

18 double crochet stitches and 11 rows
on 4" (10 cm)

Sizes

2 (4, 6, 8) years

Measurements

Width: 11.8 (12.6, 13.4, 14.2) inches (30
(32, 34, 36) cm)

Length: 15 (16.1, 17.3, 18.5) inches (38
(41, 44, 47) cm)

Buy the yarn here:

<http://shop.hobbii.com/liv-girls-top>

Pattern information

The top is crocheted down-up, and back and forth in double crochet stitches. A lace pattern is worked in the front piece and each shoulder has 2 buttons.

Abbreviations and explanations

S: stitch

ch: chain stitch



sc: single crochet stitch

dc: double crochet stitch

ss: slip stitch

hole: ch 1, skip 1 stitch, 1 dc.

Note: Double crochet stitches are worked into double crochet stitches except in the ch-space where the dc is worked under the space/the hole, so the hole is emphasized. This is not described in the chart.



Pattern

Front piece

Ch 53 (57, 61, 65) and turn by chaining 2. Turn each row with 2 ch.

Work dc until the work measures 8.3 (9.1, 9.8, 10.6) inches (21 (23, 25, 27) cm).

Mark the middle stitch.

Work according to the pattern chart or follow the written pattern below.

Work lace pattern like this:

1. row: work 26 (28, 30, 32) dc, ch 1, skip 1 s, 26 (28, 30, 32) dc = 1 hole.

2. row: work 25 (27, 29, 31) dc, ch 1, skip 1 s, 1 dc, ch 1, skip 1 s, 25 (27, 29, 31) dc = 2 holes.

3. row: 24 (26, 28, 30) dc, ch 1, skip 1 s, 3 dc, ch 1, skip 1 s, 24 (26, 28, 30) dc = 2 holes.

4. row: work 23 (25, 27, 29) dc, ch 1, skip 1 s, 1 dc in the ch-space, 3 dc, 1 dc in the ch-space, ch 1, skip 1 s, 23 (25, 27, 29) dc = 2 holes.

5. row: work 22 (24, 26, 28) dc, ch 1, skip 1 s, 1 dc in the ch-space, 2 dc, ch 1, skip 1 s, 2 dc, 1 dc in the ch-space, ch 1, skip 1 s, 22 (24, 26, 28) dc = 3 holes.

NOTE: on the 6th row, the armholes are created.

Armhole

6. row: work 7 (8, 9, 10) ss for the armhole, ch 3, 13 (15, 17, 19) dc, ch 1, skip 1 s, 1 dc in the ch-space, 2 dc, ch 1, skip 1 s, 1 dc in the ch-space, ch 1, skip 1 s, 2 dc, 1 dc in the ch-space, ch 1, skip 1 s, 13 (15, 17, 19) dc = 4 holes.

NOTE: The last 7 (8, 9, 10) sts are armhole and thus skipped. Turn by chaining 2.

7. row: work 12 (14, 16, 18) dc, ch 1, skip 1, 1 dc in ch-space, 2 dc, ch 1, skip 1 s, 1 dc in the ch-space, 2 dc, ch 1, skip 1, 2 dc, 1 dc in the ch-space, ch 1, skip 1 s, 12 (14, 16, 18) dc = 4 holes.

8. row: work 11 (13, 15, 17) dc, ch 1, skip 1, 1 dc in the ch-space, 2 dcs, ch 1, skip 1, 1 dc in the ch-space, 3 dc, 1 dc in the ch-space, ch 1, skip 1, 2 dc, 1 dc in the ch-space, ch 1, skip 1, 11 (13, 15, 17) dc = 4 holes.

9. row: work 10 (12, 14, 16) dc, ch 1, skip 1, 1 dc in the ch-space, 2 dc, ch 1, skip 1, 1 dc in the ch-space, 5 dc, 1 dc in the ch-space, ch 1, skip 1, 2 dc, 1 dc in the ch-space, ch 1, skip 1 s, 10 (12, 14, 16) dc = 4 holes.

Continue like this in pattern with 1 stitch less in each side and 2 more stitches mid front until the work measures 2.4 inches (6 cm) from armhole.

Neckline and straps

Work 9 (10, 11, 12) dc to strap, turn by chaining 2 and work straight up until the work

measures 15 (16.1, 17.3, 18.5) inches (38 (41, 44, 47) cm). Fasten off. Skip 21 sts and work 9 (10, 11, 12) dc to strap. Turn by chaining 2 and crochet straight up as you did with the first strap. Fasten off.

The back

Ch 53 (57, 61, 65) and turn by chaining 2. Turn each row by chaining 2. Work dc until the work measures the same as the front piece to armhole.

Armhole

Work 7 (8, 9, 10) ss, work dc until you have 7 (8, 9, 10) sts left, turn by chaining 2 = 39 (41, 43, 45) sts. Work straight up until the work measures 3.9 (4.3, 4.7, 5.1) inches (10 (11, 12, 13) cm) from armhole.

Neck and straps

Work 9 (10, 11, 12) dc to strap, turn by chaining 2 and work straight up until the work measures 15.3 (16.5, 17.7, 18.9) inches (39 (42, 45, 48) cm). Fasten off.

NOTE: the last inch (cm) is the button piece.


Skip 21 sts and work 9 (10, 11, 12) dc to strap. Turn by chaining 2 and crochet strap number 2 just like you worked the first strap. Fasten off.

Assembly

Sew or crochet the side seams together. Work 1 row of sc around along the edge of the armholes, the straps, the front piece and the back, as you work 2 button loops for the buttonholes on the straps of the front piece like this:

Buttonholes: work 1 sc, ch 3, skip 3 sts, work 1 (2, 3, 4) sc, ch 3, skip 3, crochet 1 sc. Sew buttons on the straps of the back.

Chart



Work dc under the chain spaces on the next row.